


Perfect VMware 3V0-41.22 Test Testking Are Leading Materials & Trusted 3V0-41.22 Clearer Explanation



P.S. Free & New 3V0-41.22 dumps are available on Google Drive shared by Lead2PassExam: https://drive.google.com/open?id=1_9FtCwETFwONrk_kHinT6ePsHnRwyql_

As we mentioned above that the Advanced Deploy VMware NSX-T Data Center 3.X (3V0-41.22) exam questions is provided to students in three different formats. The first format is Advanced Deploy VMware NSX-T Data Center 3.X PDF dumps which is printable and portable. It means students can save it on their smart devices like smartphones, tablets, and laptops. The Advanced Deploy VMware NSX-T Data Center 3.X (3V0-41.22) PDF dumps format can be printed so that candidates don't face any issues while preparing for the Advanced Deploy VMware NSX-T Data Center 3.X exam.

A lot of people have given up when they are preparing for the 3V0-41.22 exam. However, we need to realize that the genius only means hard-working all one's life. It means that if you do not persist in preparing for the 3V0-41.22 exam, you are doomed to failure. So it is of great importance for a lot of people who want to pass the exam and get the related certification to stick to studying and keep an optimistic mind. According to the survey from our company, the experts and professors from our company have designed and compiled the best 3V0-41.22 cram guide in the global market.

>> 3V0-41.22 Test Testking <<

Hot 3V0-41.22 Test Testking - Updated & Authoritative 3V0-41.22 Materials Free Download for VMware 3V0-41.22 Exam

VMware 3V0-41.22 dumps PDF version is printable and embedded with valid VMware 3V0-41.22 questions to help you get ready for the 3V0-41.22 exam quickly. Advanced Deploy VMware NSX-T Data Center 3.X (3V0-41.22) exam dumps pdf are also usable on several smart devices. You can use it anywhere at any time on your smartphones and tablets.

VMware Advanced Deploy VMware NSX-T Data Center 3.X Sample Questions (Q14-Q19):

NEW QUESTION # 14

SIMULATION

Task 3

You are asked to deploy a new instance of NSX-T into an environment with two isolated tenants. These tenants each have separate physical data center cores and have standardized on BCP as a routing protocol.

You need to:

• Configure a new Edge cluster with the following configuration detail:

Name:	edge-cluster-01
Edge cluster profile:	nsx-default-edge-high-availability-profile
Includes Edges:	nsx-edge-01 and nsx-edge-02

• Configure a Tier-0 Gateway with the following configuration detail:

Name:	TO-01
HA Mode:	Active Active
Edge cluster:	edge-cluster-01

• Configure two ECMP Uplinks to provide maximum throughput and fault tolerance. Use the following configuration detail:

- Uplink-1

Type:	External
Name:	Uplink-1
IP Address/Mask:	192.168.100.2/24
Connected to:	Uplink
Edge Node:	nsx-edge-01

- Uplink-2

Type:	External
Name:	Uplink-2
IP Address/Mask:	192.168.100.3/24
Connected to:	Uplink
Edge Node:	nsx-edge-02

• Configure BGP on the Tier-0 Gateway with the following detail:

Local AS:	65001
BGP Neighbors:	IP Address: 192.168.100.1 BFD: Disabled Remote AS Number: 65002
Additional Info:	All other values should remain at default while ensuring that ECMP is On
Source Addresses:	192.168.100.2 and 192.168.100.3

• Configure VRF Lite for the secondary tenant with the following details:

Name:	TO-01-vrf
Connected to Tier-0 Gateway:	TO-01

Complete the requested task.

Notes: Passwords are Contained in the user_readme.txt. Task 3 is dependent on the Completion Of Task and 2. Other tasks are dependent On the Completion Of this task. Do not wait for configuration changes to be applied in this task as processing may take up to 10 minutes to complete. Check back on completion. This task should take approximately 10 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To deploy a new instance of NSX-T into an environment with two isolated tenants, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > Fabric > Nodes > Edge Transport Nodes and click Add Edge VM.

Enter a name and an optional description for the edge VM. Select the compute manager, cluster, and resource pool where you want to deploy the edge VM. Click Next.

Select the deployment size and form factor for the edge VM. For this task, you can select Medium as the size and VM as the form factor. Click Next.

Select the datastore and folder where you want to store the edge VM files. Click Next.

Configure the management network settings for the edge VM. Enter a hostname, a management IP address, a default gateway, a DNS server, and a domain search list. Optionally, you can enable SSH and join the edge VM to a domain. Click Next.

Configure the transport network settings for the edge VM. Select an N-VDS as the host switch type and enter a name for it. Select an uplink profile from the drop-down menu or create a new one by clicking New Uplink Profile. Map the uplinks to the physical NICs on the edge VM. For example, map Uplink 1 to fp-eth0 and Uplink 2 to fp-eth1. Optionally, you can configure IP assignment, MTU, or LLDP for the uplinks. Click Next.

Review the configuration summary and click Finish to deploy the edge VM.

Repeat steps 2 to 8 to deploy another edge VM for redundancy.

Navigate to Networking > Tier-0 Gateway and click Add Gateway > VRF.

Enter a name and an optional description for the VRF gateway. Select an existing tier-0 gateway as the parent gateway or create a new one by clicking New Tier-0 Gateway.

Click VRF Settings and enter a VRF ID for the tenant. Optionally, you can enable EVPN settings if you want to use EVPN as the control plane protocol for VXLAN overlay networks.

Click Save to create the VRF gateway.

Repeat steps 10 to 13 to create another VRF gateway for the second tenant with a different VRF ID.

Navigate to Networking > Segments and click Add Segment.

Enter a name and an optional description for the segment. Select VLAN as the connectivity option and enter a VLAN ID for the segment. For example, enter 128 for Tenant A's first uplink VLAN segment.

Select an existing transport zone from the drop-down menu or create a new one by clicking New Transport Zone.

Click Save to create the segment.

Repeat steps 15 to 18 to create three more segments for Tenant A's second uplink VLAN segment (VLAN ID 129) and Tenant B's uplink VLAN segments (VLAN ID 158 and 159).

Navigate to Networking > Tier-0 Gateway and select the VRF gateway that you created for Tenant A.

Click Interfaces > Set > Add Interface.

Enter a name and an optional description for the interface.

Enter the IP address and mask for the external interface in CIDR format, such as 10.10.10.1/24.

In Type, select External.

In Connected To (Segment), select the VLAN segment that you created for Tenant A's first uplink VLAN segment (VLAN ID 128).

Select an edge node where you want to attach the interface, such as Edge-01.

Enter the Access VLAN ID from the list as configured for the segment, such as 128.

Click Save and then Close.

Repeat steps 21 to 28 to create another interface for Tenant A's second uplink VLAN segment (VLAN ID 129) on another edge node, such as Edge-02.

Repeat steps 20 to 29 to create two interfaces for Tenant B's uplink VLAN segments (VLAN ID 158 and 159) on each edge node using their respective VRF gateway and IP addresses.

Configure BGP on each VRF gateway using NSX UI or CLI commands12. You need to specify the local AS number, remote AS number, BGP neighbors, route redistribution, route filters, timers, authentication, graceful restart, etc., according to your requirements34.

Configure BGP on each physical router using their respective CLI commands56. You need to specify similar parameters as in step 31 and ensure that they match with their corresponding VRF gateway settings78.

Verify that BGP sessions are established between each VRF gateway and its physical router neighbors using NSX UI or CLI commands . You can also check the routing tables and BGP statistics on each device .

You have successfully deployed a new instance of NSX-T into an environment with two isolated tenants using VRF Lite and BGP.

NEW QUESTION # 15

SIMULATION

Task 14

An administrator has seen an abundance of alarms regarding high CPU usage on the NSX Managers. The administrator has successfully cleared these alarms numerous times in the past and is aware of the issue. The administrator feels that the number of alarms being produced for these events is overwhelming the log files.

You need to:

* Review CPU Sensitivity and Threshold values.

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on other tasks. This task should take approximately 5 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To review CPU sensitivity and threshold values, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > Settings > System Settings > CPU and Memory Thresholds.

You will see the current values for CPU and memory thresholds for NSX Manager, NSX Controller, and NSX Edge. These values determine the percentage of CPU and memory usage that will trigger an alarm on the NSX Manager UI.

You can modify the default threshold values by clicking Edit and entering new values in the text boxes. For example, you can increase the CPU threshold for NSX Manager from 80% to 90% to reduce the number of alarms for high CPU usage. Click Save to apply the changes.

You can also view the historical data for CPU and memory usage for each component by clicking View Usage History. You can select a time range and a granularity level to see the usage trends and patterns over time

NEW QUESTION # 16

SIMULATION

Task 12

An issue with the Tampa web servers has been reported. You would like to replicate and redirect the web traffic to a network monitoring tool outside of the NSX-T environment to further analyze the traffic.

You are asked to configure traffic replication to the monitoring software for your Tampa web overlay segments with bi-directional traffic using this detail:

Session Name:	Network-Monitor-01
Network Appliance Name/Group:	NM-01
Direction:	Bi Directional
TCP/IP Stack:	Default
Encapsulation Type:	GRE

Complete the requested configuration.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on other tasks. This task should take approximately 10 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To configure traffic replication to the monitoring software for your Tampa web overlay segments with bi-directional traffic, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to Networking > Segments and select the Tampa web overlay segment that you want to replicate the traffic from. For example, select Web-01 segment that you created in Task 2.

Click Port Mirroring > Set > Add Session and enter a name and an optional description for the port mirroring session. For example, enter Tampa-Web-Monitoring.

In the Direction section, select Bi-directional as the direction from the drop-down menu. This will replicate both ingress and egress traffic from the source to the destination.

In the Source section, click Set and select the VMs or logical ports that you want to use as the source of the traffic. For example, select Web-VM-01 and Web-VM-02 as the source VMs. Click Apply.

In the Destination section, click Set and select Remote L3 SPAN as the destination type from the drop-down menu. This will allow you to replicate the traffic to a remote destination outside of the NSX-T environment.

Enter the IP address of the destination device where you have installed the network monitoring software, such as 10.10.10.200.

Select an existing service profile from the drop-down menu or create a new one by clicking New Service Profile. A service profile defines the encapsulation type and other parameters for the replicated traffic.

Optionally, you can configure advanced settings such as TCP/IP stack, snap length, etc., for the port mirroring session.

Click Save and then Close to create the port mirroring session.

You have successfully configured traffic replication to the monitoring software for your Tampa web overlay segments with bi-directional traffic using NSX-T Manager UI.

NEW QUESTION # 17

SIMULATION

Task 6

You are asked to integrate NSX manager with LDAP to better control NSX administrators' roles and responsibilities. Ensure users can manage the NSX environment utilizing Active Directory login credentials.

You need to:

* Configure NSX Manager LDAP integration to the corp.local domain using the following configuration detail:

LDAP identity source name:	corp.local
Domain Name:	corp.local
BASE DN:	DC=corp,DC=local
Type:	Active Directory over LDAP
Active Directory host name:	controlcenter.corp.local
LDAP Protocol:	LDAP
LDAP Port:	389
User Start TLS:	disabled
Bind identity user name:	Administrator@corp.local
Bind identity password:	VMware!

* Configure the user nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

Complete the requested task.

Notes:

Passwords are contained in the user_readme.txt. You may want to move to other tasks/steps while waiting for configuration changes to be applied. This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To integrate NSX Manager with LDAP to better control NSX administrators' roles and responsibilities, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is https://<nsx-manager-ip-address>.

Navigate to System > User Management > LDAP and click Add Identity Source.

Enter a name for the identity source, such as corp.local.

Enter the domain name of your Active Directory server, such as DC=corp,DC=local.

Select Active Directory over LDAP as the type from the drop-down menu.

Click Set to configure LDAP servers. You can add up to three LDAP servers for failover support, to each domain.

Enter the hostname or IP address of your LDAP server, such as corpdcserver.corp.local.

Select LDAP as the protocol from the drop-down menu.

Enter the port number for the LDAP server, such as 389.

Click Connection Status to test the connection to the LDAP server. If successful, you will see a green check mark and a message saying "Connection successful".

Optionally, you can enable StartTLS to use encryption for the LDAP connection. To do this, toggle the Use StartTLS button and enter the certificate of the LDAP server in PEM format in the text box below.

Click Save to add the LDAP server.

Repeat steps 6 to 12 to add more LDAP servers if needed.

Enter the bind entry user name and password for the LDAP server, such as Administrator@corp.local and VMware1!.

Click Save to create the identity source.

Navigate to System > User Management > Users and Roles and click Add Role Assignment for LDAP.

Select corp.local as the domain from the drop-down menu.

Enter nsx-admin@corp.local in the search box and select it from the list that appears.

Select Enterprise Admin as the role from the drop-down menu.

Click Save to assign the role to the user.

You have successfully integrated NSX Manager with LDAP and configured nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

NEW QUESTION # 18

Task 6

You are asked to integrate NSX manager with LDAP to better control NSX administrators' roles and responsibilities. Ensure users can manage the NSX environment utilizing Active Directory login credentials.

You need to:

* Configure NSX Manager LDAP integration to the corp.local domain using the following configuration detail:

Configure NSX Manager LDAP integration to the corp.local domain using the following configuration detail:	
LDAP identity source name:	corp.local
Domain Name:	corp.local
BASE DN:	DC=corp,DC=local
Type:	Active Directory over LDAP
Active Directory host name:	controlcenter.corp.local
LDAP Protocol:	LDAP
LDAP Port:	389
User Start TLS:	disabled
Bind identity user name:	administrator@corp.local
Bind identity password:	VMware1!

* Configure the user nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

Complete the requested task.

Notes:

Passwords are contained in the user_readme.txt. You may want to move to other tasks/steps while waiting for configuration changes to be applied. This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions.

Explanation

To integrate NSX Manager with LDAP to better control NSX administrators' roles and responsibilities, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is

<https://<nsx-manager-ip-address>>.

Navigate to System > User Management > LDAP and click Add Identity Source.

Enter a name for the identity source, such as corp.local.

Enter the domain name of your Active Directory server, such as DC=corp,DC=local.

Select Active Directory over LDAP as the type from the drop-down menu.

Click Set to configure LDAP servers. You can add up to three LDAP servers for failover support, to each domain.

Enter the hostname or IP address of your LDAP server, such as corpdcserver.corp.local.

Select LDAP as the protocol from the drop-down menu.

Enter the port number for the LDAP server, such as 389.

Click Connection Status to test the connection to the LDAP server. If successful, you will see a green check mark and a message saying "Connection successful".

Optionally, you can enable StartTLS to use encryption for the LDAP connection. To do this, toggle the Use StartTLS button and enter the certificate of the LDAP server in PEM format in the text box below.

Click Save to add the LDAP server.

Repeat steps 6 to 12 to add more LDAP servers if needed.

Enter the bind entry user name and password for the LDAP server, such as Administrator@corp.local and VMware1!.

Click Save to create the identity source.

Navigate to System > User Management > Users and Roles and click Add Role Assignment for LDAP.

Select corp.local as the domain from the drop-down menu.

Enter nsx-admin@corp.local in the search box and select it from the list that appears.

Select Enterprise Admin as the role from the drop-down menu.

Click Save to assign the role to the user.

You have successfully integrated NSX Manager with LDAP and configured nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

NEW QUESTION # 19

.....

You will get real questions and accurate answers from 3V0-41.22 exam pdf torrent for your preparation of 3V0-41.22 certification.

When you choose Lead2PassExam 3V0-41.22 exam dumps, you will enjoy instant access to the 3V0-41.22 practice papers.

Moreover, free updates for 3V0-41.22 latest dumps are available for 1 year after the purchase. With the help of the 3V0-41.22 Test Engine, you can not only revisit the mistakes you made, but also can retake tests until you are satisfied. With the practice and 3V0-41.22 valid study material, you will get your VMware 3V0-41.22 certification with ease.

3V0-41.22 Clearer Explanation: <https://www.lead2passexam.com/VMware/valid-3V0-41.22-exam-dumps.html>

It is urgent for you to choose an effective and convenient method to prepare the 3V0-41.22 actual test, Why Proxy Exam at Lead2PassExam 3V0-41.22 Clearer Explanation, Lead2PassExam 3V0-41.22 Clearer Explanation is the ultimate solution to your all VMware 3V0-41.22 Clearer Explanation Designing and Implementing Cloud Data Platform Solutions related problem, VMware 3V0-41.22 Test Testking Our progress will be greater than other companies.

Finally, in How Your Child Thinks, world-renowned 3V0-41.22 child psychologist Dr, Hence this book, which offers a fundamentally different starting premise for those companies, nonprofits, social **3V0-41.22 Test Testking** entrepreneurs, and development agencies interested in developing ventures to serve the BoP.

Fast-Download 3V0-41.22 Test Testking & Trustable 3V0-41.22 Clearer Explanation & First-Grade 3V0-41.22 New Test Materials

It is urgent for you to choose an effective and convenient method to prepare the 3V0-41.22 Actual Test, Why Proxy Exam at Lead2PassExam, Lead2PassExam is the ultimate solution to your 3V0-41.22 Test Testking all VMware Designing and Implementing Cloud Data Platform Solutions related problem

Our progress will be greater than other companies, 3V0-41.22 Clearer Explanation Our company employs the first-rate expert team which is superior to others.

BTW, DOWNLOAD part of Lead2PassExam 3V0-41.22 dumps from Cloud Storage: https://drive.google.com/open?id=1_9FtCwETFwONrk_kHinT6ePsHnRwyql