

3V0-41.22 Examcollection Free Dumps, Exam 3V0-41.22 Book



P.S. Free 2025 VMware 3V0-41.22 dumps are available on Google Drive shared by VCEdumps: https://drive.google.com/open?id=1RZRdJFFG6iL_wrS9ruLUNN3L3kALcS7d

Are you looking for valid IT exam materials or study guide? You can try our free VMware 3V0-41.22 new exam collection materials. We offer free demo download for our PDF version. You can know several questions of the real test. It can make you master fundamental knowledge quickly. Our 3V0-41.22 new exam collection materials are authorized legal products. Our accuracy is nearly 100% pass which will help you clear exam.

What are the steps to follow for the registration of VMware 3V0-41.22 Exam

An exam is delivered through Pearson VUE. You can visit the Pearson VUE website to learn more.

>> 3V0-41.22 Examcollection Free Dumps <<

Free PDF Quiz 2026 3V0-41.22: Advanced Deploy VMware NSX-T Data Center 3.X – The Best Examcollection Free Dumps

This desktop practice exam software completely depicts the VMware 3V0-41.22 exam scenario with proper rules and regulations and any other plugins to access VMware 3V0-41.22 Practice Test. One such trustworthy point about exam preparation material is that it first gains your trust, and then asks you to purchase it.

VMware Advanced Deploy VMware NSX-T Data Center 3.X Sample Questions (Q14-Q19):

NEW QUESTION # 14

SIMULATION

Task 14

An administrator has seen an abundance of alarms regarding high CPU usage on the NSX Managers. The administrator has successfully cleared these alarms numerous times in the past and is aware of the issue. The administrator feels that the number of alarms being produced for these events is overwhelming the log files.

You need to:

- * Review CPU Sensitivity and Threshold values.

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on other tasks. This task should take

approximately 5 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To review CPU sensitivity and threshold values, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > Settings > System Settings > CPU and Memory Thresholds.

You will see the current values for CPU and memory thresholds for NSX Manager, NSX Controller, and NSX Edge. These values determine the percentage of CPU and memory usage that will trigger an alarm on the NSX Manager UI.

You can modify the default threshold values by clicking Edit and entering new values in the text boxes. For example, you can increase the CPU threshold for NSX Manager from 80% to 90% to reduce the number of alarms for high CPU usage. Click Save to apply the changes.

You can also view the historical data for CPU and memory usage for each component by clicking View Usage History. You can select a time range and a granularity level to see the usage trends and patterns over time

NEW QUESTION # 15

SIMULATION

Task 13

You have been asked to configure the NSX backups for the environment so that if the NSX Manager fails it can be restored with the same IP address to the original primary Data Center that is in an Active / Standby configuration. Backups should be scheduled to run once every 24 hours as well as when there are changes published to the NSX environment. Ensure that backups are completed on their respective environment. Verify the backup file has been created on the SFTP server.

* Credentials needed to complete the task:

SFTP User:	sftpuser
Password:	VMware!!
SFTP IP:	192.168.100.91
Hostname:	ubuntu-01.corp.local

You need to:

* Verify that an SFTP server is available on the network and obtain SFTP Fingerprint.

* Configure NSX Backups via NSX Appliance Backup

* Configure Scheduling Criteria

Backup Configuration Criteria

Backup Schedule:	Once backup runs 24 hours
Additional Backup Triggers:	Detect NSX configuration (5 min time interval)
Primary Data Center Configuration:	Active / Standby
Backup locations:	All backups on respective NSX environment
Additional Notes:	NSX Manager shall be restored with same IP address
Directory Path:	/data
Passphrase:	VMware!!

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on other tasks. This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To configure the NSX backups for the environment, you need to follow these steps:

Verify that an SFTP server is available on the network and obtain SFTP fingerprint. You can use the `search_web("SFTP server availability")` tool to find some information on how to set up and check an SFTP server. You can also use the `ssh-keyscan` command to get the fingerprint of the SFTP server. For example, `ssh-keyscan -t ecdsa sftp_server` will return the ECDSA key of the `sftp_server`. You can compare this key with the one displayed on the NSX Manager UI when you configure the backup settings.

Configure NSX Backups via NSX Appliance Backup. Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>. Select System > Lifecycle Management > Backup & Restore. Click Edit under the SFTP Server label to configure your SFTP server. Enter the FQDN or IP address of the backup file server, such as 10.10.10.100. The protocol text box is already filled in. SFTP is the only supported protocol. Change the default port if necessary. The default TCP port is 22.

In the Directory Path text box, enter the absolute directory path where the backups will be stored, such as `/data`. The directory must already exist and cannot be the root directory (`/`). Avoid using path drive letters or spaces in directory names; they are not

supported. In the Passphrase text box, enter a passphrase that will be used to encrypt and decrypt the backup files, such as VMware1!. Click Save to create the backup configuration.

Configure Scheduling Criteria. On the Backup & Restore page, click Edit under the Schedule label to configure your backup schedule. Select Enabled from the drop-down menu to enable scheduled backups. Select Daily from the Frequency drop-down menu to run backups once every 24 hours. Select a time from the Time drop-down menu to specify when the backup will start, such as 12:00 AM. Select Enabled from the Additional Backup Trigger drop-down menu to run backups when there are changes published to the NSX environment. Click Save to create the backup schedule.

Verify that a backup file has been created on the SFTP server. On the Backup & Restore page, click Start Backup to run a manual backup and verify that it completes successfully. You should see a message saying "Backup completed successfully". You can also check the status and details of your backups on this page, such as backup size, duration, and timestamp. Alternatively, you can log in to your SFTP server and check if there is a backup file in your specified directory path, such as /data.

NEW QUESTION # 16

SIMULATION

Task 3

You are asked to deploy a new instance of NSX-T into an environment with two isolated tenants. These tenants each have separate physical data center cores and have standardized on BCP as a routing protocol.

You need to:

• Configure a new Edge cluster with the following configuration detail:	
Name:	edge-cluster-01
Edge cluster profile:	nsx-default-edge-high-availability-profile
Includes Edges:	nsx-edge-01 and nsx-edge-02
• Configure a Tier-0 Gateway with the following configuration detail:	
Name:	TO-01
HA Mode:	Active Active
Edge cluster:	edge-cluster-01
• Configure two ECMP Uplinks to provide maximum throughput and fault tolerance. Use the following configuration detail:	
◦ Uplink-1	
Type:	External
Name:	Uplink-1
IP Address/Mask:	192.168.100.2/24
Connected to:	Uplink
Edge Node:	nsx-edge-01
• Uplink-2	
Type:	External
Name:	Uplink-2
IP Address/Mask:	192.168.100.3/24
Connected to:	Uplink
Edge Node:	nsx-edge-02
• Configure BCP on the Tier-0 Gateway with the following detail:	
Local AS:	65001
BCP Neighbors:	IP Address: 192.168.100.1 BFD: Disabled Remote AS Number: 65002
Additional info:	All other values should remain at default while ensuring that ECMP is On
Source Addresses:	192.168.100.2 and 192.168.100.3
• Configure VRF Lite for the secondary tenant with the following detail:	
Name:	TO-01-vrf
Connected to Tier-0 Gateway:	TO-01

Complete the requested task.

Notes: Passwords are Contained in the user_readme.txt. Task 3 is dependent on the Completion Of Task and 2. Other tasks are dependent On the Completion Of this task. Do not wait for configuration changes to be applied in this task as processing may take up to 10 minutes to complete. Check back on completion. This task should take approximately 10 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To deploy a new instance of NSX-T into an environment with two isolated tenants, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > Fabric > Nodes > Edge Transport Nodes and click Add Edge VM.

Enter a name and an optional description for the edge VM. Select the compute manager, cluster, and resource pool where you want to deploy the edge VM. Click Next.

Select the deployment size and form factor for the edge VM. For this task, you can select Medium as the size and VM as the form factor. Click Next.

Select the datastore and folder where you want to store the edge VM files. Click Next.

Configure the management network settings for the edge VM. Enter a hostname, a management IP address, a default gateway, a DNS server, and a domain search list. Optionally, you can enable SSH and join the edge VM to a domain. Click Next.

Configure the transport network settings for the edge VM. Select an N-VDS as the host switch type and enter a name for it. Select an uplink profile from the drop-down menu or create a new one by clicking New Uplink Profile. Map the uplinks to the physical NICs on the edge VM. For example, map Uplink 1 to fp-eth0 and Uplink 2 to fp-eth1. Optionally, you can configure IP assignment, MTU, or LLDP for the uplinks. Click Next.

Review the configuration summary and click Finish to deploy the edge VM.

Repeat steps 2 to 8 to deploy another edge VM for redundancy.

Navigate to Networking > Tier-0 Gateway and click Add Gateway > VRF.

Enter a name and an optional description for the VRF gateway. Select an existing tier-0 gateway as the parent gateway or create a new one by clicking New Tier-0 Gateway.

Click VRF Settings and enter a VRF ID for the tenant. Optionally, you can enable EVPN settings if you want to use EVPN as the control plane protocol for VXLAN overlay networks.

Click Save to create the VRF gateway.

Repeat steps 10 to 13 to create another VRF gateway for the second tenant with a different VRF ID.

Navigate to Networking > Segments and click Add Segment.

Enter a name and an optional description for the segment. Select VLAN as the connectivity option and enter a VLAN ID for the segment. For example, enter 128 for Tenant A's first uplink VLAN segment.

Select an existing transport zone from the drop-down menu or create a new one by clicking New Transport Zone.

Click Save to create the segment.

Repeat steps 15 to 18 to create three more segments for Tenant A's second uplink VLAN segment (VLAN ID 129) and Tenant B's uplink VLAN segments (VLAN ID 158 and 159).

Navigate to Networking > Tier-0 Gateway and select the VRF gateway that you created for Tenant A.

Click Interfaces > Set > Add Interface.

Enter a name and an optional description for the interface.

Enter the IP address and mask for the external interface in CIDR format, such as 10.10.10.1/24.

In Type, select External.

In Connected To (Segment), select the VLAN segment that you created for Tenant A's first uplink VLAN segment (VLAN ID 128).

Select an edge node where you want to attach the interface, such as Edge-01.

Enter the Access VLAN ID from the list as configured for the segment, such as 128.

Click Save and then Close.

Repeat steps 21 to 28 to create another interface for Tenant A's second uplink VLAN segment (VLAN ID 129) on another edge node, such as Edge-02.

Repeat steps 20 to 29 to create two interfaces for Tenant B's uplink VLAN segments (VLAN ID 158 and 159) on each edge node using their respective VRF gateway and IP addresses.

Configure BGP on each VRF gateway using NSX UI or CLI commands¹². You need to specify the local AS number, remote AS number, BGP neighbors, route redistribution, route filters, timers, authentication, graceful restart, etc., according to your requirements³⁴.

Configure BGP on each physical router using their respective CLI commands⁵⁶. You need to specify similar parameters as in step 31 and ensure that they match with their corresponding VRF gateway settings⁷⁸.

Verify that BGP sessions are established between each VRF gateway and its physical router neighbors using NSX UI or CLI commands. You can also check the routing tables and BGP statistics on each device.

You have successfully deployed a new instance of NSX-T into an environment with two isolated tenants using VRF Lite and BGP.

NEW QUESTION # 17

SIMULATION

Task 6

You are asked to integrate NSX manager with LDAP to better control NSX administrators' roles and responsibilities. Ensure users can manage the NSX environment utilizing Active Directory login credentials.

You need to:

- * Configure NSX Manager LDAP integration to the corp.local domain using the following configuration detail:

• Configure NSX Manager LDAP integration to the corp.local domain using the following configuration detail:	
LDAP identity source name:	corp.local
Domain Name:	corp.local
BASE DN:	DC=corp,DC=local
Type:	Active Directory over LDAP
Active Directory host name:	controlcenter.corp.local
LDAP Protocol:	LDAP
LDAP Port:	389
User Start TLS:	disabled
Bind identity user name:	administrator@corp.local
Bind identity password:	VMware!!

* Configure the user nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

Complete the requested task.

Notes:

Passwords are contained in the user_readme.txt. You may want to move to other tasks/steps while waiting for configuration changes to be applied. This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To integrate NSX Manager with LDAP to better control NSX administrators' roles and responsibilities, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > User Management > LDAP and click Add Identity Source.

Enter a name for the identity source, such as corp.local.

Enter the domain name of your Active Directory server, such as DC=corp,DC=local.

Select Active Directory over LDAP as the type from the drop-down menu.

Click Set to configure LDAP servers. You can add up to three LDAP servers for failover support, to each domain.

Enter the hostname or IP address of your LDAP server, such as corpdcserver.corp.local.

Select LDAP as the protocol from the drop-down menu.

Enter the port number for the LDAP server, such as 389.

Click Connection Status to test the connection to the LDAP server. If successful, you will see a green check mark and a message saying "Connection successful".

Optionally, you can enable StartTLS to use encryption for the LDAP connection. To do this, toggle the Use StartTLS button and enter the certificate of the LDAP server in PEM format in the text box below.

Click Save to add the LDAP server.

Repeat steps 6 to 12 to add more LDAP servers if needed.

Enter the bind entry user name and password for the LDAP server, such as Administrator@corp.local and VMware!!.

Click Save to create the identity source.

Navigate to System > User Management > Users and Roles and click Add Role Assignment for LDAP.

Select corp.local as the domain from the drop-down menu.

Enter nsx-admin@corp.local in the search box and select it from the list that appears.

Select Enterprise Admin as the role from the drop-down menu.

Click Save to assign the role to the user.

You have successfully integrated NSX Manager with LDAP and configured nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

NEW QUESTION # 18

Task 5

You are asked to configure a micro-segmentation policy for a new 3-tier web application that will be deployed to the production environment.

You need to:

- Configure Tags with the following configuration detail:

Tag Name	Member
Boston	Boston-web-01a, Boston-web-02a, Boston-app-01a, Boston-db-01a
Boston-Web	Boston-web-01a, Boston-web-02a
Boston-App	Boston-app-01a
Boston-DB	Boston-db-01a

- Configure Security Groups (use tags to define group criteria) with the following configuration detail:

Boston

Boston Web-Servers

Boston App-Servers

Boston DB-Servers

- Configure the Distributed Firewall Exclusion List with the following configuration detail:

Virtual Machine:

core-A

- Configure Policy & DFW Rules with the following configuration detail:

Policy Name: Boston-Web-Application
 Applied to: Boston
 New Services: TCP-8443, TCP-3051

- Policy detail:

Rule Name	Source	Destination	Service	Action
Any-to-Web	Any	Boston Web-Servers	HTTP,HTTPS	ALLOW
Web-to-App	Boston Web-Servers	Boston App-Servers	TCP-8443	ALLOW
App-to-DB	Boston App-Servers	Boston DB-Servers	TCP-3051	ALLOW

Notes:

Passwords are contained in the user_readme.txt. Do not wait for configuration changes to be applied in this task as processing may take some time.

The task steps are not dependent on one another. Subsequent tasks may require completion of this task. This task should take approximately 25 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions.

NEW QUESTION # 19

.....

The authoritative, efficient, and thoughtful service of 3V0-41.22 learning question will give you the best user experience, and you can also get what you want with our study materials. I hope our study materials can accompany you to pursue your dreams. If you can choose 3V0-41.22 test guide, we will be very happy. We look forward to meeting you. You can choose your favorite our study materials version according to your feelings. When you use 3V0-41.22 Test Guide, you can also get our services at any time. We will try our best to solve your problems for you. I believe that you will be more inclined to choose a good service product, such as 3V0-41.22 learning question. After all, everyone wants to be treated warmly and kindly, and hope to learn in a more pleasant mood.

Exam 3V0-41.22 Book: <https://www.vcedumps.com/3V0-41.22-examcollection.html>

- Test 3V0-41.22 Preparation ☐ 3V0-41.22 Exams Dumps ☐ Hot 3V0-41.22 Questions ☐ Go to website ➡ www.vceengine.com ☐ open and search for ☐ 3V0-41.22 ☐ to download for free ☐ 3V0-41.22 Cost Effective Dumps
- 2026 100% Free 3V0-41.22 –High Pass-Rate 100% Free Examcollection Free Dumps | Exam Advanced Deploy VMware NSX-T Data Center 3.X Book ☐ Enter 「 www.pdfvce.com 」 and search for ✓ 3V0-41.22 ☐ ✓ ☐ to download for free ☐ 3V0-41.22 Valid Braindumps Sheet
- 3V0-41.22 Examcollection Free Dumps 100% Pass | Latest Exam 3V0-41.22 Book: Advanced Deploy VMware NSX-T Data Center 3.X ☐ Immediately open ➡ www.troytecdumps.com ☐ ☐ and search for ➡ 3V0-41.22 ☐ to obtain a free download ☐ 3V0-41.22 Valid Test Format
- Test 3V0-41.22 Question ☐ 3V0-41.22 Reliable Exam Book ☐ 3V0-41.22 Valid Braindumps Sheet ☐ Open website ➡ www.pdfvce.com ☐ and search for ➡ 3V0-41.22 ☐ for free download ☐ 3V0-41.22 Cost Effective Dumps
- VMware - Authoritative 3V0-41.22 Examcollection Free Dumps ➡ Open 《 www.prepawaypdf.com 》 and search for (3V0-41.22) to download exam materials for free ☐ Test 3V0-41.22 Question
- TOP 3V0-41.22 Examcollection Free Dumps 100% Pass | The Best Exam Advanced Deploy VMware NSX-T Data Center 3.X Book Pass for sure ☐ Go to website ➡ www.pdfvce.com ☐ open and search for ✓ 3V0-41.22 ☐ ✓ ☐ to download for free ☐ Exams 3V0-41.22 Torrent

- P.S. Free & New 3V0-41.22 dumps are available on Google Drive shared by VCEDumps: https://drive.google.com/open?id=1RZRdJFFG6iL_wrS9ruLUNN3L3kALcS7d

P.S. Free & New 3V0-41.22 dumps are available on Google Drive shared by VCEDumps: https://drive.google.com/open?id=1RZRdJFFG6iL_wrS9ruLUNN3L3kALcS7d