

3V0-41.22 valid dumps - 3V0-41.22 exam simulator - 3V0-41.22 study torrent



2026 Latest Dumpcollection 3V0-41.22 PDF Dumps and 3V0-41.22 Exam Engine Free Share: <https://drive.google.com/open?id=1xdfUcnEC7GRt5OxDxrVGFgoWThxsAv1H>

Dumpcollection is a website that can provide all information about different IT certification exam. Dumpcollection can provide you with the best and latest exam resources. To choose Dumpcollection you can feel at ease to prepare your VMware 3V0-41.22 exam. Our training materials can guarantee you 100% to pass VMware certification 3V0-41.22 exam, if not, we will give you a full refund and exam practice questions and answers will be updated quickly, but this is almost impossible to happen. Dumpcollection can help you pass VMware Certification 3V0-41.22 Exam and can also help you in the future about your work. Although there are many ways to help you achieve your purpose, selecting Dumpcollection is your wisest choice. Having Dumpcollection can make you spend shorter time less money and with greater confidence to pass the exam, and we also provide you with a free one-year after-sales service.

VMware 3V0-41.22 Certification Exam is designed for IT professionals who want to validate their skills in deploying and managing VMware NSX-T Data Center 3.x environments. This advanced certification exam covers a wide range of topics such as NSX-T components, installation, configuration, and management. Passing 3V0-41.22 exam demonstrates that you have the knowledge and skills required to deploy and manage advanced NSX-T Data Center environments.

VMware 3V0-41.22 certification is ideal for professionals who want to demonstrate their expertise in NSX-T Data Center 3.X deployment and management. Advanced Deploy VMware NSX-T Data Center 3.X certification validates the candidate's ability to design, deploy, and manage NSX-T Data Center 3.X solutions. Advanced Deploy VMware NSX-T Data Center 3.X certification is also useful for professionals who want to enhance their career prospects and increase their earning potential.

>> **Reliable 3V0-41.22 Exam Syllabus** <<

Test 3V0-41.22 Online, 3V0-41.22 Download Free Dumps

To cope with the fast growing market, we will always keep advancing and offer our clients the most refined technical expertise and excellent services about our 3V0-41.22 exam questions. In the meantime, all your legal rights will be guaranteed after buying our 3V0-41.22 Study Materials. For many years, we have always put our customers in top priority. Not only we offer the best 3V0-41.22 training prep, but also our sincere and considerate attitude is praised by numerous of our customers.

VMware 3V0-41.22 certification exam consists of 60 multiple-choice questions that need to be completed within 120 minutes. 3V0-41.22 exam is available in English and Japanese language. The passing score for 3V0-41.22 Exam is 300 out of 500. VMware recommends that candidates take the VMware NSX-T Data Center: Install, Configure, Manage [V3.0] course before attempting this certification exam.

VMware Advanced Deploy VMware NSX-T Data Center 3.X Sample Questions (Q13-Q18):

NEW QUESTION # 13

Task 5

You are asked to configure a micro-segmentation policy for a new 3-tier web application that will be deployed to the production environment.

You need to:

• Configure Tags with the following configuration detail:	
Tag Name	Member
Boston	Boston-web-01a, Boston-web-02a, Boston-app-01a, Boston-db-01a
Boston-Web	Boston-web-01a, Boston-web-02a
Boston-App	Boston-app-01a
Boston-DB	Boston-db-01a

• Configure Security Groups (use tags to define group criteria) with the following configuration detail:	
Security Group Name	Members
Boston	
Boston Web-Servers	
Boston App-Servers	
Boston DB-Servers	

• Configure the Distributed Firewall Exclusion List with the following configuration detail:	
Virtual Machine:	Exclusion List
core-A	

• Configure Policy & DFW Rules with the following configuration detail:		
Policy Name:	Applied to:	New Services:
Boston-Web-Application	Boston	TCP-8443, TCP-3051

• Policy detail:				
Rule Name	Source	Destination	Service	Action
Any-to-Web	Any	Boston Web-Servers	HTTP,HTTPS	ALLOW
Web-to-App	Boston Web-Servers	Boston App-Servers	TCP-8443	ALLOW
App-to-DB	Boston App-Servers	Boston DB-Servers	TCP-3051	ALLOW

Notes:

Passwords are contained in the user_readme.txt. Do not wait for configuration changes to be applied in this task as processing may take some time.

The task steps are not dependent on one another. Subsequent tasks may require completion of this task. This task should take approximately 25 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions.

NEW QUESTION # 14

Task 8

You are tasked With troubleshooting the NSX IPSec VPN service Which has been reported down. Verify the current NSX configuration is deployed and resolve any issues.

You need to:

* Verify the present configuration as provided below:

NSX IPSec Session Name:	
Remote IP:	192.168.140.2
Local Networks:	10.10.10.0/24
Remote Networks:	10.10.20.0/24
Pre-shared Key:	VMware!!VMware!!

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on another. This task Should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions.

Explanation

To troubleshoot the NSX IPSec VPN service that has been reported down, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is

<https://<nsx-manager-ip-address>>.

Navigate to Networking > VPN > IPSec VPN and select the IPSec VPN session that is down. You can identify the session by its name, local endpoint, remote endpoint, and status.

Click Show IPSec Statistics and view the details of the IPSec VPN session failure. You can see the error message, the tunnel state, the IKE and ESP status, and the statistics of the traffic sent and received.

Compare the configuration details of the IPSec VPN session with the expected configuration as provided below. Check for any discrepancies or errors in the parameters such as local and remote endpoints, local and remote networks, IKE and ESP profiles, etc.

If you find any configuration errors, click Actions > Edit and modify the parameters accordingly. Click Save to apply the changes.

If you do not find any configuration errors, check the connectivity and firewall rules between the local and remote endpoints. You can use ping or traceroute commands from the NSX Edge CLI to test the connectivity. You can also use show service ipsec command to check the status of IPSec VPN service on the NSX Edge.

If you find any connectivity or firewall issues, resolve them by adjusting the network settings or firewall rules on the NSX Edge or the third-party device.

After resolving the issues, verify that the IPSec VPN session is up and running by refreshing the IPSec VPN page on the NSX Manager UI. You can also use show service ipsec sp and show service ipsec sa commands on the NSX Edge CLI to check the status of security policy and security association for the IPSec VPN session.

NEW QUESTION # 15

SIMULATION

Task 3

You are asked to deploy a new instance of NSX-T into an environment with two isolated tenants. These tenants each have separate physical data center cores and have standardized on BCP as a routing protocol.

You need to:

• Configure a new Edge cluster with the following configuration detail:	
Name:	edge-cluster-01
Edge cluster profile:	nsx-default-edge-high-availability-profile
Includes Edges:	nsx-edge-01 and nsx-edge-02

• Configure a Tier-0 Gateway with the following configuration detail:	
Name:	TO-01
HA Mode:	Active Active
Edge cluster:	edge-cluster-01

• Configure two ECMP Uplinks to provide maximum throughput and fault tolerance. Use the following configuration detail:	
◦ Uplink-1	
Type:	External
Name:	Uplink-1
IP Address/Mask:	192.168.100.2/24
Connected to:	Uplink
Edge Node:	nsx-edge-01

• Uplink-2	
Type:	External
Name:	Uplink-2
IP Address/Mask:	192.168.100.3/24
Connected to:	Uplink
Edge Node:	nsx-edge-02

• Configure BGP on the Tier-0 Gateway with the following detail:	
Local AS:	65001
BGP Neighbors:	IP Address: 192.168.100.1 BFD: Disabled Remote AS Number: 65002
Additional Info:	All other values should remain at default while ensuring that ECMP is On
Source Addresses:	192.168.100.2 and 192.168.100.3

• Configure VRF Lite for the secondary tenant with the following detail:	
Name:	TO-01-vrf
Connected to Tier-0 Gateway:	TO-01

Complete the requested task.

Notes: Passwords are Contained in the user_readme.txt. Task 3 is dependent on the Completion Of Task and 2. Other tasks are

dependent On the Completion Of this task. Do not wait for configuration changes to be applied in this task as processing may take up to 10 minutes to complete. Check back on completion. This task should take approximately 10 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To deploy a new instance of NSX-T into an environment with two isolated tenants, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > Fabric > Nodes > Edge Transport Nodes and click Add Edge VM.

Enter a name and an optional description for the edge VM. Select the compute manager, cluster, and resource pool where you want to deploy the edge VM. Click Next.

Select the deployment size and form factor for the edge VM. For this task, you can select Medium as the size and VM as the form factor. Click Next.

Select the datastore and folder where you want to store the edge VM files. Click Next.

Configure the management network settings for the edge VM. Enter a hostname, a management IP address, a default gateway, a DNS server, and a domain search list. Optionally, you can enable SSH and join the edge VM to a domain. Click Next.

Configure the transport network settings for the edge VM. Select an N-VDS as the host switch type and enter a name for it. Select an uplink profile from the drop-down menu or create a new one by clicking New Uplink Profile. Map the uplinks to the physical NICs on the edge VM. For example, map Uplink 1 to fp-eth0 and Uplink 2 to fp-eth1. Optionally, you can configure IP assignment, MTU, or LLDP for the uplinks. Click Next.

Review the configuration summary and click Finish to deploy the edge VM.

Repeat steps 2 to 8 to deploy another edge VM for redundancy.

Navigate to Networking > Tier-0 Gateway and click Add Gateway > VRF.

Enter a name and an optional description for the VRF gateway. Select an existing tier-0 gateway as the parent gateway or create a new one by clicking New Tier-0 Gateway.

Click VRF Settings and enter a VRF ID for the tenant. Optionally, you can enable EVPN settings if you want to use EVPN as the control plane protocol for VXLAN overlay networks.

Click Save to create the VRF gateway.

Repeat steps 10 to 13 to create another VRF gateway for the second tenant with a different VRF ID.

Navigate to Networking > Segments and click Add Segment.

Enter a name and an optional description for the segment. Select VLAN as the connectivity option and enter a VLAN ID for the segment. For example, enter 128 for Tenant A's first uplink VLAN segment.

Select an existing transport zone from the drop-down menu or create a new one by clicking New Transport Zone.

Click Save to create the segment.

Repeat steps 15 to 18 to create three more segments for Tenant A's second uplink VLAN segment (VLAN ID 129) and Tenant B's uplink VLAN segments (VLAN ID 158 and 159).

Navigate to Networking > Tier-0 Gateway and select the VRF gateway that you created for Tenant A.

Click Interfaces > Set > Add Interface.

Enter a name and an optional description for the interface.

Enter the IP address and mask for the external interface in CIDR format, such as 10.10.10.1/24.

In Type, select External.

In Connected To (Segment), select the VLAN segment that you created for Tenant A's first uplink VLAN segment (VLAN ID 128).

Select an edge node where you want to attach the interface, such as Edge-01.

Enter the Access VLAN ID from the list as configured for the segment, such as 128.

Click Save and then Close.

Repeat steps 21 to 28 to create another interface for Tenant A's second uplink VLAN segment (VLAN ID 129) on another edge node, such as Edge-02.

Repeat steps 20 to 29 to create two interfaces for Tenant B's uplink VLAN segments (VLAN ID 158 and 159) on each edge node using their respective VRF gateway and IP addresses.

Configure BGP on each VRF gateway using NSX UI or CLI commands¹². You need to specify the local AS number, remote AS number, BGP neighbors, route redistribution, route filters, timers, authentication, graceful restart, etc., according to your requirements³⁴.

Configure BGP on each physical router using their respective CLI commands⁵⁶. You need to specify similar parameters as in step 31 and ensure that they match with their corresponding VRF gateway settings⁷⁸.

Verify that BGP sessions are established between each VRF gateway and its physical router neighbors using NSX UI or CLI commands . You can also check the routing tables and BGP statistics on each device .

You have successfully deployed a new instance of NSX-T into an environment with two isolated tenants using VRF Lite and BGP.

NEW QUESTION # 16

Task 6

You are asked to integrate NSX manager with LDAP to better control NSX administrators' roles and responsibilities. Ensure users can manage the NSX environment utilizing Active Directory login credentials.

You need to:

* Configure NSX Manager LDAP integration to the corp.local domain using the following configuration detail:

• Configure NSX Manager LDAP integration to the corp.local domain using the following configuration detail:	
LDAP identity source name:	corp.local
Domain Name:	corp.local
BASE DN:	DC=corp,DC=local
Type:	Active Directory over LDAP
Active Directory host name:	controlcenter.corp.local
LDAP Protocol:	LDAP
LDAP Port:	389
User Start TLS:	disabled
Bind identity user name:	administrator@corp.local
Bind identity password:	VMware!!

* Configure the user nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

Complete the requested task.

Notes:

Passwords are contained in the user_readme.txt. You may want to move to other tasks/steps while waiting for configuration changes to be applied. This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions.

Explanation

To integrate NSX Manager with LDAP to better control NSX administrators' roles and responsibilities, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is

<https://<nsx-manager-ip-address>>.

Navigate to System > User Management > LDAP and click Add Identity Source.

Enter a name for the identity source, such as corp.local.

Enter the domain name of your Active Directory server, such as DC=corp,DC=local.

Select Active Directory over LDAP as the type from the drop-down menu.

Click Set to configure LDAP servers. You can add up to three LDAP servers for failover support, to each domain.

Enter the hostname or IP address of your LDAP server, such as corpdcserver.corp.local.

Select LDAP as the protocol from the drop-down menu.

Enter the port number for the LDAP server, such as 389.

Click Connection Status to test the connection to the LDAP server. If successful, you will see a green check mark and a message saying "Connection successful".

Optionally, you can enable StartTLS to use encryption for the LDAP connection. To do this, toggle the Use StartTLS button and enter the certificate of the LDAP server in PEM format in the text box below.

Click Save to add the LDAP server.

Repeat steps 6 to 12 to add more LDAP servers if needed.

Enter the bind entry user name and password for the LDAP server, such as Administrator@corp.local and VMware!!.

Click Save to create the identity source.

Navigate to System > User Management > Users and Roles and click Add Role Assignment for LDAP.

Select corp.local as the domain from the drop-down menu.

Enter nsx-admin@corp.local in the search box and select it from the list that appears.

Select Enterprise Admin as the role from the drop-down menu.

Click Save to assign the role to the user.

You have successfully integrated NSX Manager with LDAP and configured nsx-admin@corp.local Active Directory account as an Enterprise Admin access role.

NEW QUESTION # 17

SIMULATION

Task 7

you are asked to create a custom QoS profile to prioritize the traffic on the phoenix-VLAN segment and limit the rate of ingress traffic.

You need to:

* Create a custom QoS profile for the phoenix-VLAN using the following configuration detail:

• Create a custom QoS profile for the phoenix-VLAN using the following configuration detail:	
Name:	ingress-phoenix-qos-profile
Priority:	0
Class of Service:	0
Ingress traffic rate limits:	100 Mbps for average, 200 Mbps for peak

* Apply the profile on the 'phoenix-VLAN' segment

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt.

take approximately 5 minutes to complete.

Subsequent tasks may require the completion of this task. This task should

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To create a custom QoS profile to prioritize the traffic on the phoenix-VLAN segment and limit the rate of ingress traffic, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to Networking > Segments > Switching Profiles and click Add Switching Profile. Select QoS as the profile type.

Enter a name and an optional description for the QoS profile, such as phoenix-QoS.

In the Mode section, select Untrusted as the mode from the drop-down menu. This will allow you to set a custom DSCP value for the outbound IP header of the traffic on the segment.

In the Priority section, enter 46 as the DSCP value. This will mark the traffic with Expedited Forwarding (EF) per-hop behavior, which is typically used for high-priority applications such as voice or video.

In the Class of Service section, enter 5 as the CoS value. This will map the DSCP value to a CoS value that can be used by VLAN-based logical ports or physical switches to prioritize the traffic.

In the Ingress section, enter 1000000 as the Average Bandwidth in Kbps. This will limit the rate of inbound traffic from the VMs to the logical network to 1 Mbps.

Optionally, you can also configure Peak Bandwidth and Burst Size settings for the ingress traffic, which will allow some burst traffic above the average bandwidth limit for a short duration.

Click Save to create the QoS profile.

Navigate to Networking > Segments and select the phoenix-VLAN segment that you want to apply the QoS profile to.

Click Actions > Apply Profile and select phoenix-QoS as the switching profile that you want to apply to the segment.

Click Apply to apply the profile to the segment.

You have successfully created a custom QoS profile and applied it to the phoenix-VLAN segment.

NEW QUESTION # 18

.....

Test 3V0-41.22 Online: https://www.dumpcollection.com/3V0-41.22_braindumps.html

- Free PDF Quiz VMware - 3V0-41.22 - The Best Reliable Advanced Deploy VMware NSX-T Data Center 3.X Exam Syllabus ☐ The page for free download of ☀ 3V0-41.22 ☀ ☐ on **【 www.easy4engine.com 】** will open immediately ☐ 3V0-41.22 Exam Experience
- Reliable 3V0-41.22 Braindumps Book ☐ Exam 3V0-41.22 Cost ☐ 3V0-41.22 Exam Experience ☐ Search for ➡ 3V0-41.22 ☐ and download exam materials for free through ➡ www.pdfvce.com ☐ ☐ ☐ New 3V0-41.22 Test Pass4sure
- Exam 3V0-41.22 Vce Format ☐ New 3V0-41.22 Test Pass4sure ☐ 3V0-41.22 Updated CBT ☐ Search for “3V0-41.22” and easily obtain a free download on ➡ www.exam4labs.com ◀ ☐ 3V0-41.22 Test Review
- PDF 3V0-41.22 Cram Exam ☐ Latest 3V0-41.22 Braindumps Free ☐ New Guide 3V0-41.22 Files ☐ Easily obtain free download of ➤ 3V0-41.22 ☐ by searching on ☐ www.pdfvce.com ☐ ☐ PDF 3V0-41.22 Cram Exam
- VMware - Trustable Reliable 3V0-41.22 Exam Syllabus ☐ Open ➡ www.vce4dumps.com ☐ and search for ☐ 3V0-41.22 ☐ to download exam materials for free ☐ Real 3V0-41.22 Torrent
- 3V0-41.22 Updated CBT ☐ 3V0-41.22 Reliable Test Preparation ☐ Exam 3V0-41.22 Review ☐ Open ➡ www.pdfvce.com ◀ and search for 《 3V0-41.22 》 to download exam materials for free ☐ Test 3V0-41.22 Pass4sure
- Exam 3V0-41.22 Format ☐ Real 3V0-41.22 Torrent ☐ 3V0-41.22 Reliable Test Preparation ☐ Search for ✓ 3V0-41.22 ☐ ✓ ☐ on ➡ www.vce4dumps.com ☐ ☐ ☐ immediately to obtain a free download ☐ Latest 3V0-41.22 Braindumps Free

- Real 3V0-41.22 Torrent ☞ Real 3V0-41.22 Torrent ☐ Exam 3V0-41.22 Torrent ☐ Search for [3V0-41.22] and download it for free immediately on 《 www.pdfvce.com 》 ☐ New Guide 3V0-41.22 Files
- VMware - Trustable Reliable 3V0-41.22 Exam Syllabus ☐ Search for 《 3V0-41.22 》 and download it for free immediately on ➡ www.verifeddumps.com ☐ ☐ PDF 3V0-41.22 Cram Exam
- Latest 3V0-41.22 Braindumps Free ☐ 3V0-41.22 Test Review ☐ 3V0-41.22 Valid Exam Discount ☐ Download ▷ 3V0-41.22 ◁ for free by simply searching on ☼ www.pdfvce.com ☐ ☼ ☐ ☐ Latest 3V0-41.22 Braindumps Free
- 100% Pass 2026 VMware First-grade 3V0-41.22: Reliable Advanced Deploy VMware NSX-T Data Center 3.X Exam Syllabus ☐ Open { www.troytecdumps.com } enter ▶ 3V0-41.22 ◀ and obtain a free download ☐ Reliable 3V0-41.22 Braindumps Book
- www.skudci.com, bbs.t-firefly.com, bbs.t-firefly.com, mutouzyz.com, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, wanderlog.com, 1.gdsfjd.net, www.sxrsedu.cn, bbs.t-firefly.com, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, Disposable vapes

BONUS!!! Download part of Dumpcollection 3V0-41.22 dumps for free: <https://drive.google.com/open?id=1xdfUcnEC7GRt5OxDxVGFgoWThxsAv1H>