


Download VMware 3V0-41.22 Exam Dumps Instantly



DOWNLOAD the newest PrepAwayTest 3V0-41.22 PDF dumps from Cloud Storage for free: https://drive.google.com/open?id=1gPfs0Q-nKIEtClwdBDmdXSkZ_m6itsMP

Now you can trust PrepAwayTest 3V0-41.22 exam questions as these Advanced Deploy VMware NSX-T Data Center 3.X (3V0-41.22) exam questions have already helped countless candidates in their 3V0-41.22 exam preparation. They easily got success in their challenging and dream VMware 3V0-41.22 Certification Exam. Now they have become certified VMware professionals and offer their services to top world brands.

VMware 3V0-41.22 exam consists of 60 multiple-choice questions that need to be answered within 120 minutes. 3V0-41.22 exam focuses on various topics, including NSX-T architecture, installation, configuration, and management. 3V0-41.22 exam also covers NSX-T security, load balancing, and troubleshooting. Candidates are required to have a deep understanding of NSX-T components and their interdependencies, as well as the ability to design and deploy NSX-T infrastructure.

VMware 3V0-41.22 Certification Exam is a valuable credential that demonstrates the candidates' expertise in advanced deployment of VMware NSX-T Data Center 3.X. Advanced Deploy VMware NSX-T Data Center 3.X certification is recognized globally and is highly respected by IT professionals and employers. Achieving this certification can open up new career opportunities and increase the earning potential of candidates.

>> 3V0-41.22 Pdf Braindumps <<

3V0-41.22 Valid Exam Simulator & New 3V0-41.22 Test Materials

We assure that you can not only purchase high-quality 3V0-41.22 prep guide but also gain great courage & trust from us. A lot of online education platform resources need to be provided by the user registration to use after purchase, but it is simple on our website. We provide free demo of 3V0-41.22 Guide Torrent, you can download any time without registering. Fast delivery—after payment you can receive our 3V0-41.22 exam torrent no more than 10 minutes, so that you can learn fast and efficiently. What are you waiting for? Just come and buy our 3V0-41.22 exam questions!

VMware 3V0-41.22 certification exam assesses the candidate's ability to deploy, configure, and manage the VMware NSX-T Data Center 3.X environment. 3V0-41.22 exam covers a range of topics, including NSX-T Data Center architecture, installation and

configuration, networking and security, automation, and troubleshooting. 3V0-41.22 Exam is designed to test the candidate's knowledge and skills in deploying and managing VMware NSX-T Data Center 3.X in a complex enterprise environment.

VMware Advanced Deploy VMware NSX-T Data Center 3.X Sample Questions (Q11-Q16):

NEW QUESTION # 11

SIMULATION

Task 3

You are asked to deploy a new instance of NSX-T into an environment with two isolated tenants. These tenants each have separate physical data center cores and have standardized on BCP as a routing protocol.

You need to:

• Configure a new Edge cluster with the following configuration detail:	
Name:	edge-cluster-01
Edge cluster profile:	nsx-default-edge-high-availability-profile
Includes Edges:	nsx-edge-01 and nsx-edge-02
• Configure a Tier-0 Gateway with the following configuration detail:	
Name:	TO-01
HA Mode:	Active Active
Edge cluster:	edge-cluster-01
• Configure two ECMP Uplinks to provide maximum throughput and fault tolerance. Use the following configuration details:	
◦ Uplink-1	
Type:	External
Name:	Uplink-1
IP Address/Mask:	192.168.100.2/24
Connected to:	Uplink
Edge Node:	nsx-edge-01
◦ Uplink-2	
Type:	External
Name:	Uplink-2
IP Address/Mask:	192.168.100.3/24
Connected to:	Uplink
Edge Node:	nsx-edge-02
• Configure BGP on the Tier-0 Gateway with the following detail:	
Local AS:	65001
BGP Neighbors:	IP Address: 192.168.100.1 BFD: Disabled Remote AS Number: 65002
Additional Info:	All other values should remain at default while ensuring that ECMP is On
Source Addresses:	192.168.100.2 and 192.168.100.3
• Configure VRF Lite for the secondary tenant with the following detail:	
Name:	TO-01-vrf
Connected to Tier-0 Gateway:	TO-01

Complete the requested task.

Notes: Passwords are Contained in the user_readme.txt. Task 3 is dependent on the Completion Of Task and 2. Other tasks are dependent On the Completion Of this task. Do not wait for configuration changes to be applied in this task as processing may take up to 10 minutes to complete. Check back on completion. This task should take approximately 10 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To deploy a new instance of NSX-T into an environment with two isolated tenants, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > Fabric > Nodes > Edge Transport Nodes and click Add Edge VM.

Enter a name and an optional description for the edge VM. Select the compute manager, cluster, and resource pool where you want to deploy the edge VM. Click Next.

Select the deployment size and form factor for the edge VM. For this task, you can select Medium as the size and VM as the form factor. Click Next.

Select the datastore and folder where you want to store the edge VM files. Click Next.

Configure the management network settings for the edge VM. Enter a hostname, a management IP address, a default gateway, a

DNS server, and a domain search list. Optionally, you can enable SSH and join the edge VM to a domain. Click Next.

Configure the transport network settings for the edge VM. Select an N-VDS as the host switch type and enter a name for it. Select an uplink profile from the drop-down menu or create a new one by clicking New Uplink Profile. Map the uplinks to the physical NICs on the edge VM. For example, map Uplink 1 to fp-eth0 and Uplink 2 to fp-eth1. Optionally, you can configure IP assignment, MTU, or LLDP for the uplinks. Click Next.

Review the configuration summary and click Finish to deploy the edge VM.

Repeat steps 2 to 8 to deploy another edge VM for redundancy.

Navigate to Networking > Tier-0 Gateway and click Add Gateway > VRF.

Enter a name and an optional description for the VRF gateway. Select an existing tier-0 gateway as the parent gateway or create a new one by clicking New Tier-0 Gateway.

Click VRF Settings and enter a VRF ID for the tenant. Optionally, you can enable EVPN settings if you want to use EVPN as the control plane protocol for VXLAN overlay networks.

Click Save to create the VRF gateway.

Repeat steps 10 to 13 to create another VRF gateway for the second tenant with a different VRF ID.

Navigate to Networking > Segments and click Add Segment.

Enter a name and an optional description for the segment. Select VLAN as the connectivity option and enter a VLAN ID for the segment. For example, enter 128 for Tenant A's first uplink VLAN segment.

Select an existing transport zone from the drop-down menu or create a new one by clicking New Transport Zone.

Click Save to create the segment.

Repeat steps 15 to 18 to create three more segments for Tenant A's second uplink VLAN segment (VLAN ID 129) and Tenant B's uplink VLAN segments (VLAN ID 158 and 159).

Navigate to Networking > Tier-0 Gateway and select the VRF gateway that you created for Tenant A.

Click Interfaces > Set > Add Interface.

Enter a name and an optional description for the interface.

Enter the IP address and mask for the external interface in CIDR format, such as 10.10.10.1/24.

In Type, select External.

In Connected To (Segment), select the VLAN segment that you created for Tenant A's first uplink VLAN segment (VLAN ID 128).

Select an edge node where you want to attach the interface, such as Edge-01.

Enter the Access VLAN ID from the list as configured for the segment, such as 128.

Click Save and then Close.

Repeat steps 21 to 28 to create another interface for Tenant A's second uplink VLAN segment (VLAN ID 129) on another edge node, such as Edge-02.

Repeat steps 20 to 29 to create two interfaces for Tenant B's uplink VLAN segments (VLAN ID 158 and 159) on each edge node using their respective VRF gateway and IP addresses.

Configure BGP on each VRF gateway using NSX UI or CLI commands¹². You need to specify the local AS number, remote AS number, BGP neighbors, route redistribution, route filters, timers, authentication, graceful restart, etc., according to your requirements³⁴.

Configure BGP on each physical router using their respective CLI commands⁵⁶. You need to specify similar parameters as in step 31 and ensure that they match with their corresponding VRF gateway settings⁷⁸.

Verify that BGP sessions are established between each VRF gateway and its physical router neighbors using NSX UI or CLI commands . You can also check the routing tables and BGP statistics on each device .

You have successfully deployed a new instance of NSX-T into an environment with two isolated tenants using VRF Lite and BGP.

NEW QUESTION # 12

Task 15

You have been asked to enable logging so that the global operations team can view inv Realize Log Insight that their Service Level Agreements are being met for all network traffic that is going in and out of the NSX environment. This NSX environment is an Active / Active two Data Center design utilizing N-VDSwith BCP.

You need to ensure successful logging for the production NSX-T environment.

You need to:

Verify via putty with SSH that the administrator can connect to all NSX-Transport Nodes. You will use the credentials identified in Putty (admin).

Verify that there is no current active logging enabled by reviewing that directory is empty `~/var/log/syslog`

Enable NSX Manager Cluster logging

Select multiple configuration choices that could be appropriate success criteria Enable NSX Edge Node logging Validate logs are generated on each selected appliance by reviewing the `~/var/log/syslog` Complete the requested task.

Notes: Passwords are contained in the user `_readme.txt`. complete.

These task steps are dependent on one another. This task should take approximately 10 minutes to complete.

Answer:**Explanation:**

See the Explanation part of the Complete Solution and step by step instructions.

Explanation

To enable logging for the production NSX-T environment, you need to follow these steps:

Verify via putty with SSH that the administrator can connect to all NSX-Transport Nodes. You can use the credentials identified in Putty (admin) to log in to each transport node. For example, you can use the following command to connect to the sfo01w01en01 edge transport node:ssh admin@sfo01w01en01.

You should see a welcome message and a prompt to enter commands.

Verify that there is no current active logging enabled by reviewing that directory is empty

-/var/log/syslog-. You can use thelscommand to list the files in the /var/log/syslog directory. For example, you can use the following command to check the sfo01w01en01 edge transport node:ls

/var/log/syslog. You should see an empty output if there is no active logging enabled.

Enable NSX Manager Cluster logging. You can use thesearch_web("NSX Manager Cluster logging configuration")tool to find some information on how to configure remote logging for NSX Manager Cluster. One of the results isNSX-T Syslog Configuration

Revisited - vDives, which provides the following steps:

Navigate to System> Fabric > Profiles > Node Profiles then select All NSX Nodes then under Syslog Servers click +ADD Enter the IP or FQDN of the syslog server, the Port and Protocol and the desired Log Level then click ADD Select multiple configuration choices that could be appropriate success criteria. You can use thesearch_web("NSX-T logging success criteria")tool to find some information on how to verify and troubleshoot logging for NSX-T. Some of the possible success criteria are:

The syslog server receives log messages from all NSX nodes

The log messages contain relevant information such as timestamp, hostname, facility, severity, message ID, and message content The log messages are formatted and filtered according to the configured settings The log messages are encrypted and authenticated if using secure protocols such as TLS or LI-TLS Enable NSX Edge Node logging. You can use thesearch_web("NSX Edge Node logging configuration")tool to find some information on how to configure remote logging for NSX Edge Node.

One of the results isConfigure Remote Logging - VMware Docs, which provides the following steps:

Run the following command to configure a log server and the types of messages to send to the log server. Multiple facilities or message IDs can be specified as a comma delimited list, without spaces.

```
set logging-server <hostname-or-ip-address [-port]> proto <proto> level <level> [facility <facility>]
[messageid <messageid>] [serverca <filename>] [clientca <filename>] [certificate <filename>] [key
<filename>] [structured-data <structured-data>]
```

Validate logs are generated on each selected appliance by reviewing the "/var/log/syslog". You can use thecatortailcommands to view the contents of the /var/log/syslog file on each appliance. For example, you can use the following command to view the last 10 lines of the sfo01w01en01 edge transport node:tail -n 10 /var/log/syslog. You should see log messages similar to this:

```
2023-04-06T12:34:56+00:00 sfo01w01en01 user.info nsx-edge[1234]: 2023-04-06T12:34:56Z nsx-edge[1234]: INFO:
[nsx@6876 comp="nsx-edge" subcomp="nsx-edge" level="INFO" security="False"] Message from nsx-edge You have
successfully enabled logging for the production NSX-T environment.
```

NEW QUESTION # 13**SIMULATION****Task 14**

An administrator has seen an abundance of alarms regarding high CPU usage on the NSX Managers. The administrator has successfully cleared these alarms numerous times in the past and is aware of the issue. The administrator feels that the number of alarms being produced for these events is overwhelming the log files.

You need to:

- * Review CPU Sensitivity and Threshold values.

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on other tasks. This task should take approximately 5 minutes to complete.

Answer:**Explanation:**

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To review CPU sensitivity and threshold values, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is https://<nsx-manager-ip-address>.

Navigate to System> Settings > System Settings > CPU and Memory Thresholds.

You will see the current values for CPU and memory thresholds for NSX Manager, NSX Controller, and NSX Edge. These values determine the percentage of CPU and memory usage that will trigger an alarm on the NSX Manager UI.

You can modify the default threshold values by clicking Edit and entering new values in the text boxes. For example, you can increase the CPU threshold for NSX Manager from 80% to 90% to reduce the number of alarms for high CPU usage. Click Save to apply the changes.

You can also view the historical data for CPU and memory usage for each component by clicking View Usage History. You can select a time range and a granularity level to see the usage trends and patterns over time

NEW QUESTION # 14

SIMULATION

Task 10

You have been notified by the Web Team that they cannot get to any northbound networks from their Tampa web servers that are deployed on an NSX-T network segment. The Tampa web VM's however can access each other.

You need to:

* Troubleshoot to find out why the Tampa web servers cannot communicate to any northbound networks and resolve the issue.

Complete the requested task. TO verify your work. ping the Control Center @ 192.168.110.10 Notes: Passwords are contained in the user_readme.txt. This task is dependent on Task 4. Some exam candidates may have already completed this task if they had done more than the minimum required in Task 4. This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To troubleshoot why the Tampa web servers cannot communicate to any northbound networks, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to Networking > Tier-0 Gateway and select the tier-0 gateway that connects the NSX-T network segment to the northbound networks. For example, select T0-GW-01.

Click Interfaces > Set and verify the configuration details of the interfaces. Check for any discrepancies or errors in the parameters such as IP address, subnet mask, MTU, etc.

If you find any configuration errors, click Edit and modify the parameters accordingly. Click Save to apply the changes.

If you do not find any configuration errors, check the connectivity and firewall rules between the tier-0 gateway and the northbound networks. You can use ping or traceroute commands from the NSX Edge CLI or the vSphere Web Client to test the connectivity.

You can also use show service router command to check the status of the routing service on the NSX Edge.

If you find any connectivity or firewall issues, resolve them by adjusting the network settings or firewall rules on the NSX Edge or the northbound devices.

After resolving the issues, verify that the Tampa web servers can communicate to any northbound networks by pinging the Control Center @ 192.168.110.10 from one of the web servers.

NEW QUESTION # 15

Task 10

You have been notified by the Web Team that they cannot get to any northbound networks from their Tampa web servers that are deployed on an NSX-T network segment. The Tampa web VM's however can access each other.

You need to:

* Troubleshoot to find out why the Tampa web servers cannot communicate to any northbound networks and resolve the issue.

Complete the requested task. TO verify your work. ping the Control Center @ 192.168.110.10 Notes: Passwords are contained in the user_readme.txt. This task is dependent on Task 4. Some exam candidates may have already completed this task if they had done more than the minimum required in Task 4.

This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions.

Explanation

To troubleshoot why the Tampa web servers cannot communicate to any northbound networks, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is

<https://<nsx-manager-ip-address>>.

Navigate to Networking > Tier-0 Gateway and select the tier-0 gateway that connects the NSX-T network segment to the northbound networks. For example, select T0-GW-01.

Click Interfaces > Set and verify the configuration details of the interfaces. Check for any discrepancies or errors in the parameters

such as IP address, subnet mask, MTU, etc.

If you find any configuration errors, click Edit and modify the parameters accordingly. Click Save to apply the changes.

If you do not find any configuration errors, check the connectivity and firewall rules between the tier-0 gateway and the northbound networks. You can use ping or traceroute commands from the NSX Edge CLI or the vSphere Web Client to test the connectivity. You can also use show service router command to check the status of the routing service on the NSX Edge.

If you find any connectivity or firewall issues, resolve them by adjusting the network settings or firewall rules on the NSX Edge or the northbound devices.

After resolving the issues, verify that the Tampa web servers can communicate to any northbound networks by pinging the Control Center @ 192.168.110.10 from one of the web servers.

NEW QUESTION # 16

.....

3V0-41.22 Valid Exam Simulator: <https://www.prepawaytest.com/VMware/3V0-41.22-practice-exam-dumps.html>

- Advanced Deploy VMware NSX-T Data Center 3.X exam test engine - 3V0-41.22 exam prep material - Advanced Deploy VMware NSX-T Data Center 3.X practice questions Download ⇒ 3V0-41.22 ⇐ for free by simply searching on ✓ www.validtorrent.com ✓ 3V0-41.22 Reliable Braindumps Files
- New 3V0-41.22 Test Practice Mock 3V0-41.22 Exam New 3V0-41.22 Test Practice Search for 《 3V0-41.22 》 on [www.pdfvce.com] immediately to obtain a free download 3V0-41.22 Reliable Exam Tips
- VMware 3V0-41.22 Pdf Braindumps - Pass Guaranteed Quiz 2026 Advanced Deploy VMware NSX-T Data Center 3.X Realistic Valid Exam Simulator Open 【 www.troytecdumps.com 】 enter 《 3V0-41.22 》 and obtain a free download 3V0-41.22 Latest Exam Vce
- High-quality 3V0-41.22 – 100% Free Pdf Braindumps | 3V0-41.22 Valid Exam Simulator Search for ☀ 3V0-41.22 ☀ and easily obtain a free download on ▷ www.pdfvce.com ◁ Exam 3V0-41.22 Consultant
- Free PDF 3V0-41.22 - Advanced Deploy VMware NSX-T Data Center 3.X Authoritative Pdf Braindumps [www.vceengine.com] is best website to obtain “ 3V0-41.22 ” for free download 3V0-41.22 Reliable Exam Tips
- The Best VMware 3V0-41.22 Exam Training materials Simply search for 3V0-41.22 for free download on ⇒ www.pdfvce.com ⇐ 3V0-41.22 Latest Test Materials
- 3V0-41.22 Valid Test Vce Free New 3V0-41.22 Test Practice 3V0-41.22 Valid Test Registration Search for ⇒ 3V0-41.22 ⇐ and download exam materials for free through 「 www.easy4engine.com 」 Exam 3V0-41.22 Consultant
- 3V0-41.22 Pass4sure Questions - 3V0-41.22 Actual Test - 3V0-41.22 Practice Training Immediately open www.pdfvce.com and search for ▷ 3V0-41.22 ◁ to obtain a free download 3V0-41.22 Reliable Exam Tips
- Free PDF 3V0-41.22 - Advanced Deploy VMware NSX-T Data Center 3.X Authoritative Pdf Braindumps Simply search for ▶ 3V0-41.22 ◀ for free download on ► www.prepawayete.com 3V0-41.22 Reliable Exam Tips
- 3V0-41.22 Pass4sure Questions - 3V0-41.22 Actual Test - 3V0-41.22 Practice Training Search for { 3V0-41.22 } on ⇒ www.pdfvce.com ⇐ immediately to obtain a free download 3V0-41.22 Test Engine
- High-quality 3V0-41.22 – 100% Free Pdf Braindumps | 3V0-41.22 Valid Exam Simulator Search for ▷ 3V0-41.22 ◁ on ☀ www.vce4dumps.com ☀ immediately to obtain a free download Exam 3V0-41.22 Consultant
- myportal.utt.edu.tt, www.stes.tyc.edu.tw, www.stes.tyc.edu.tw, www.skudci.com, confengine.com, akdmx.momentum.com.ro, teachladakh.com, zeno.co.tz, shebolivia.com, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, myportal.utt.edu.tt, Disposable vapes

P.S. Free & New 3V0-41.22 dumps are available on Google Drive shared by PrepAwayTest: https://drive.google.com/open?id=1gPfsOQ-nKIETClwdBDmdXSkZ_m6itsMP