


Pass Guaranteed VMware - 3V0-41.22 - Fantastic Advanced Deploy VMware NSX-T Data Center 3.X Test Collection Pdf



BONUS!!! Download part of TorrentValid 3V0-41.22 dumps for free: <https://drive.google.com/open?id=1-SDlaf0pqCkfuawrtb9K0acMI9XPaIM1>

The VMware 3V0-41.22 certification exam is a valuable credential that often comes with certain personal and professional benefits. For many VMware professionals, the Advanced Deploy VMware NSX-T Data Center 3.X (3V0-41.22) certification exam is not just a valuable way to boost their skills but also Advanced Deploy VMware NSX-T Data Center 3.X certification exam gives them an edge in the job market or the corporate ladder. There are other several advantages that successful VMware 3V0-41.22 Exam candidates can gain after passing the VMware 3V0-41.22 exam.

VMware 3V0-41.22 certification exam covers a wide range of topics, including NSX-T Data Center architecture and components, NSX-T Data Center installation and configuration, logical switching and routing, NSX-T Data Center security, and more. 3V0-41.22 exam is a combination of multiple-choice, drag-and-drop, and scenario-based questions that test the candidate's knowledge and practical skills in NSX-T Data Center 3.x. 3V0-41.22 Exam Duration is two hours, and the passing score is 300 out of 500 points.

>> 3V0-41.22 Test Collection Pdf <<

Dumps 3V0-41.22 Download - New 3V0-41.22 Exam Answers

The 3V0-41.22 Mock Exams not just give you a chance to self-access before you actually sit for the certification exam, but also help you get an idea of the VMware exam structure. It is well known that students who do a mock version of an exam benefit from it immensely. Some VMware certified experts even say that it can be a more beneficial way to prepare for the Advanced Deploy VMware NSX-T Data Center 3.X exam than spending the same amount of time studying.

VMware Advanced Deploy VMware NSX-T Data Center 3.X Sample Questions (Q12-Q17):

NEW QUESTION # 12

Task 11

upon testing the newly configured distributed firewall policy for the Boston application, it has been discovered that the Boston-Web virtual machines can be "pinged" via ICMP from the main console. Corporate policy does not allow pings to the Boston VMs.

You need to:

- * Troubleshoot ICMP traffic and make any necessary changes to the Boston application security policy.

Complete the requested task.

Notes: Passwords are contained in the user _readme.txt. This task is dependent on Task 5.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions.

Explanation

To troubleshoot ICMP traffic and make any necessary changes to the Boston application security policy, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is

<https://<nsx-manager-ip-address>>.

Navigate to Security > Distributed Firewall and select the firewall policy that applies to the Boston application. For example, select Boston-web-Application.

Click Show IPSec Statistics and view the details of the firewall rule hits and logs. You can see which rules are matching the ICMP traffic and which actions are taken by the firewall.

If you find that the ICMP traffic is allowed by a rule that is not intended for it, you can edit the rule and change the action to Drop or Reject. You can also modify the source, destination, or service criteria of the rule to make it more specific or exclude the ICMP traffic.

If you find that the ICMP traffic is not matched by any rule, you can create a new rule and specify the action as Drop or Reject. You can also specify the source, destination, or service criteria of the rule to match only the ICMP traffic from the main console to the Boston web VMs.

After making the changes, click Publish to apply the firewall policy.

Verify that the ICMP traffic is blocked by pinging the Boston web VMs from the main console again. You should see a message saying "Request timed out" or "Destination unreachable".

NEW QUESTION # 13

SIMULATION

Task 9

TO prepare for Virtual machine migration from VLAN-backed port groups to an overlay segment in NSX, a test bridge has been configured. The bridge is not functioning, and the -Bridge-VM- is not responding to ICMP requests from the main console.

You need to:

- * Troubleshoot the configuration and make necessary changes to restore access to the application.

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on another. This task should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To troubleshoot the bridge configuration and restore access to the application, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to Networking > Segments and select the overlay segment that is bridged to the VLAN-backed port group. For example, select Web-01 segment that you created in Task 2.

Click Bridge > Set and verify the configuration details of the bridge. Check for any discrepancies or errors in the parameters such as bridge name, bridge ID, VLAN ID, edge node, etc.

If you find any configuration errors, click Edit and modify the parameters accordingly. Click Save to apply the changes.

If you do not find any configuration errors, check the connectivity and firewall rules between the overlay segment and the VLAN-backed port group. You can use ping or traceroute commands from the NSX Edge CLI or the vSphere Web Client to test the connectivity. You can also use show service bridge command to check the status of the bridge service on the NSX Edge.

If you find any connectivity or firewall issues, resolve them by adjusting the network settings or firewall rules on the NSX Edge or the vSphere Distributed Switch.

After resolving the issues, verify that the bridge is functioning and the Bridge-VM is responding to ICMP requests from the main console. You can also check the MAC addresses learned by the bridge on both sides of the network using show service bridge mac command on the NSX Edge CLI.

NEW QUESTION # 14

SIMULATION

Task 8

You are tasked With troubleshooting the NSX IPSec VPN service Which has been reported down. Verify the current NSX configuration is deployed and resolve any issues.

You need to:

* Verify the present configuration as provided below:

NSX IPSec Session Name:	IPSEC
Remote IP:	192.168.140.2
Local Networks:	10.10.10.0/24
Remote Networks:	10.10.20.0/24
Pre-shared Key:	VMware!!VMware!!

Complete the requested task.

Notes: Passwords are contained in the user_readme.txt. This task is not dependent on another. This task Should take approximately 15 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To troubleshoot the NSX IPSec VPN service that has been reported down, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to Networking > VPN > IPSec VPN and select the IPSec VPN session that is down. You can identify the session by its name, local endpoint, remote endpoint, and status.

Click Show IPSec Statistics and view the details of the IPSec VPN session failure. You can see the error message, the tunnel state, the IKE and ESP status, and the statistics of the traffic sent and received.

Compare the configuration details of the IPSec VPN session with the expected configuration as provided below. Check for any discrepancies or errors in the parameters such as local and remote endpoints, local and remote networks, IKE and ESP profiles, etc.

If you find any configuration errors, click Actions > Edit and modify the parameters accordingly. Click Save to apply the changes.

If you do not find any configuration errors, check the connectivity and firewall rules between the local and remote endpoints. You can use ping or traceroute commands from the NSX Edge CLI to test the connectivity. You can also use show service ipsec command to check the status of IPSec VPN service on the NSX Edge.

If you find any connectivity or firewall issues, resolve them by adjusting the network settings or firewall rules on the NSX Edge or the third-party device.

After resolving the issues, verify that the IPSec VPN session is up and running by refreshing the IPSec VPN page on the NSX Manager UI. You can also use show service ipsec sp and show service ipsec sa commands on the NSX Edge CLI to check the status of security policy and security association for the IPSec VPN session.

NEW QUESTION # 15

SIMULATION

Task 4

You are tasked with creating a logical load balancer for several web servers that were recently deployed.

You need to:

• Create a standalone Tier-1 gateway with the following configuration detail:	
Name:	TI-LB
Linked Tier-0 Gateway:	None
Edge Cluster:	lb-edge-cluster
Service Interface:	Name: TI-LB IP Address / Mask: 192.168.220.10/24 Connected To (Segment): Columbus-L5
Static Route:	Add a default gateway to 192.168.220.1
• Create a load balancer and attach it to the newly created Tier-1 gateway with the following configuration detail:	
Name:	web-lb
Size:	small
Attachment:	TI-LB
• Configure the load balancer with the following configuration detail:	
◦ Create an HTTP application profile with the following configuration detail:	
Name:	web-lb-app-profile
• Create an HTTP application profile with the following configuration detail:	
Name:	web-lb-app-redirect-profile
Redirection:	HTTP to HTTPS Redirection
• Create an HTTP monitor with the following configuration detail:	
Name:	web-lb-monitor
Port:	80

• Create an L7 HTTP virtual server with the following configuration detail:	
Name:	web-lb-virtual-server
IP Address:	192.168.220.20
Port:	80
Load Balancer:	web-lb
Server Pool:	None
Application Profile:	web-lb-app-redirect-profile

• Create an L4 TCP virtual server with the following configuration detail:	
Name:	web-lb-virtual-server-https
IP Address:	192.168.220.20
Port:	443
Load Balancer:	web-lb
Server Pool:	Columbus-web-servers
Application Profile:	default-tcp-lb-app-profile

Complete the requested task.

Notes:

Passwords are contained in the user_readme.txt. Do not wait for configuration changes to be applied in this task as processing may take some time to complete. This task should take up to 35 minutes to complete and is required for subsequent tasks.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To create a logical load balancer for several web servers, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to Networking > Load Balancing > Load Balancers and click Add Load Balancer.

Enter a name and an optional description for the load balancer. Select the tier-1 gateway where you want to attach the load balancer from the drop-down menu or create a new one by clicking New Tier-1 Gateway. Click Save.

Navigate to Networking > Load Balancing > Application Profiles and click Add Application Profile.

Enter a name and an optional description for the application profile. Select HTTP as the application type from the drop-down menu.

Optionally, you can configure advanced settings such as persistence, X-Forwarded-For, SSL offloading, etc., for the application profile. Click Save.

Navigate to Networking > Load Balancing > Monitors and click Add Monitor.

Enter a name and an optional description for the monitor. Select HTTP as the protocol from the drop-down menu. Optionally, you can configure advanced settings such as interval, timeout, fall count, rise count, etc., for the monitor. Click Save.

Navigate to Networking > Load Balancing > Server Pools and click Add Server Pool.

Enter a name and an optional description for the server pool. Select an existing application profile from the drop-down menu or create a new one by clicking New Application Profile. Select an existing monitor from the drop-down menu or create a new one by clicking New Monitor. Optionally, you can configure advanced settings such as algorithm, SNAT translation mode, TCP multiplexing, etc., for the server pool. Click Save.

Click Members > Set > Add Member and enter the IP address and port number of each web server that you want to add to the server pool. For example, enter 192.168.10.10:80 and 192.168.10.11:80 for two web servers listening on port 80. Click Save and then Close.

Navigate to Networking > Load Balancing > Virtual Servers and click Add Virtual Server.

Enter a name and an optional description for the virtual server. Enter the IP address and port number of the virtual server that will receive the client requests, such as 10.10.10.100:80. Select HTTP as the service profile from the drop-down menu or create a new one by clicking New Service Profile. Select an existing server pool from the drop-down menu or create a new one by clicking New Server Pool. Optionally, you can configure advanced settings such as access log, connection limit, rate limit, etc., for the virtual server. Click Save.

You have successfully created a logical load balancer for several web servers using NSX-T Manager UI.

NEW QUESTION # 16

SIMULATION

Task 3

You are asked to deploy a new instance of NSX-T into an environment with two isolated tenants. These tenants each have separate physical data center cores and have standardized on BCP as a routing protocol.

You need to:

• Configure a new Edge cluster with the following configuration detail:	
Name:	edge-cluster-01
Edge cluster profile:	nsx-default-edge-high-availability-profile
Includes Edges:	nsx-edge-01 and nsx-edge-02

• Configure a Tier-0 Gateway with the following configuration detail:	
Name:	T0-01
HA Mode:	Active Active
Edge cluster:	edge-cluster-01
• Configure two ECMP Uplinks to provide maximum throughput and fault tolerance. Use the following configuration detail:	
o Uplink-1	
Type:	External
Name:	Uplink-1
IP Address/Mask:	192.168.100.2/24
Connected to:	Uplink
Edge Node:	nsx-edge-01
• Uplink-2	
Type:	External
Name:	Uplink-2
IP Address/Mask:	192.168.100.3/24
Connected to:	Uplink
Edge Node:	nsx-edge-02
• Configure BGP on the Tier-0 Gateway with the following detail:	
Local AS:	65001
BGP Neighbors:	IP Address: 192.168.100.1 BFD: Disabled Remote AS Number: 65002
Additional Info:	All other values should remain at default while ensuring that ECMP is On
Source Addresses:	192.168.100.2 and 192.168.100.3
• Configure VRF Lite for the secondary tenant with the following detail:	
Name:	T0-01-vrf
Connected to Tier-0 Gateway:	T0-01

Complete the requested task.

Notes: Passwords are Contained in the user_readme.txt. Task 3 is dependent on the Completion Of Task and 2. Other tasks are dependent On the Completion Of this task. Do not wait for configuration changes to be applied in this task as processing may take up to 10 minutes to complete. Check back on completion. This task should take approximately 10 minutes to complete.

Answer:

Explanation:

See the Explanation part of the Complete Solution and step by step instructions Explanation:

To deploy a new instance of NSX-T into an environment with two isolated tenants, you need to follow these steps:

Log in to the NSX Manager UI with admin credentials. The default URL is <https://<nsx-manager-ip-address>>.

Navigate to System > Fabric > Nodes > Edge Transport Nodes and click Add Edge VM.

Enter a name and an optional description for the edge VM. Select the compute manager, cluster, and resource pool where you want to deploy the edge VM. Click Next.

Select the deployment size and form factor for the edge VM. For this task, you can select Medium as the size and VM as the form factor. Click Next.

Select the datastore and folder where you want to store the edge VM files. Click Next.

Configure the management network settings for the edge VM. Enter a hostname, a management IP address, a default gateway, a DNS server, and a domain search list. Optionally, you can enable SSH and join the edge VM to a domain. Click Next.

Configure the transport network settings for the edge VM. Select an N-VDS as the host switch type and enter a name for it. Select an uplink profile from the drop-down menu or create a new one by clicking New Uplink Profile. Map the uplinks to the physical NICs on the edge VM. For example, map Uplink 1 to fp-eth0 and Uplink 2 to fp-eth1. Optionally, you can configure IP assignment, MTU, or LLDP for the uplinks. Click Next.

Review the configuration summary and click Finish to deploy the edge VM.

Repeat steps 2 to 8 to deploy another edge VM for redundancy.

Navigate to Networking > Tier-0 Gateway and click Add Gateway > VRF.

Enter a name and an optional description for the VRF gateway. Select an existing tier-0 gateway as the parent gateway or create a new one by clicking New Tier-0 Gateway.

Click VRF Settings and enter a VRF ID for the tenant. Optionally, you can enable EVPN settings if you want to use EVPN as the control plane protocol for VXLAN overlay networks.

Click Save to create the VRF gateway.

Repeat steps 10 to 13 to create another VRF gateway for the second tenant with a different VRF ID.

Navigate to Networking > Segments and click Add Segment.

Enter a name and an optional description for the segment. Select VLAN as the connectivity option and enter a VLAN ID for the segment. For example, enter 128 for Tenant A's first uplink VLAN segment.

Select an existing transport zone from the drop-down menu or create a new one by clicking New Transport Zone.

Click Save to create the segment.

Repeat steps 15 to 18 to create three more segments for Tenant A's second uplink VLAN segment (VLAN ID 129) and Tenant B's uplink VLAN segments (VLAN ID 158 and 159).

Navigate to Networking > Tier-0 Gateway and select the VRF gateway that you created for Tenant A.

Click Interfaces > Set > Add Interface.

Enter a name and an optional description for the interface.

Enter the IP address and mask for the external interface in CIDR format, such as 10.10.10.1/24.

In Type, select External.

In Connected To (Segment), select the VLAN segment that you created for Tenant A's first uplink VLAN segment (VLAN ID 128).

Select an edge node where you want to attach the interface, such as Edge-01.

Enter the Access VLAN ID from the list as configured for the segment, such as 128.

Click Save and then Close.

Repeat steps 21 to 28 to create another interface for Tenant A's second uplink VLAN segment (VLAN ID 129) on another edge node, such as Edge-02.

Repeat steps 20 to 29 to create two interfaces for Tenant B's uplink VLAN segments (VLAN ID 158 and 159) on each edge node using their respective VRF gateway and IP addresses.

Configure BGP on each VRF gateway using NSX UI or CLI commands¹². You need to specify the local AS number, remote AS number, BGP neighbors, route redistribution, route filters, timers, authentication, graceful restart, etc., according to your requirements³⁴.

Configure BGP on each physical router using their respective CLI commands⁵⁶. You need to specify similar parameters as in step 31 and ensure that they match with their corresponding VRF gateway settings⁷⁸.

Verify that BGP sessions are established between each VRF gateway and its physical router neighbors using NSX UI or CLI commands. You can also check the routing tables and BGP statistics on each device.



You have successfully deployed a new instance of NSX-T into an environment with two isolated tenants using VRF Lite and BGP.

NEW QUESTION # 17

.....

In modern time, new ideas and knowledge continue to emerge, our 3V0-41.22 training prep has always been keeping up with the trend. Besides, they are accessible to both novice and experienced customers equally. Some customer complained to and worried that the former 3V0-41.22 training prep is not suitable to the new test, which is wrong because we keep the new content into the 3V0-41.22 practice materials by experts.

Dumps 3V0-41.22 Download: <https://www.torrentvalid.com/3V0-41.22-valid-braindumps-torrent.html>

- Fast Download 3V0-41.22 Test Collection Pdf| Easy To Study and Pass Exam at first attempt - Excellent VMware Advanced Deploy VMware NSX-T Data Center 3.X  Immediately open ➡ www.exams4collection.com ☐ and search for ➡ 3V0-41.22 ☐ to obtain a free download ☐ Reliable 3V0-41.22 Exam Voucher
- Hot 3V0-41.22 Test Collection Pdf| High Pass-Rate Dumps 3V0-41.22 Download: Advanced Deploy VMware NSX-T Data Center 3.X 100% Pass ☐ Easily obtain free download of 【 3V0-41.22 】 by searching on ➤ www.pdfvce.com ☐ 3V0-41.22 Reliable Test Testking
- 3V0-41.22 Examcollection Questions Answers ☐ 3V0-41.22 Valid Test Vce Free ☐ Reliable 3V0-41.22 Exam Voucher ☐ Search for ➡ 3V0-41.22 ⇐ and obtain a free download on 《 www.getvalidtest.com 》 ☐ 3V0-41.22 Dump
- 3V0-41.22 Exam Study Guide ☐ Examcollection 3V0-41.22 Vce ☐ Reliable 3V0-41.22 Practice Questions ☐ Download { 3V0-41.22 } for free by simply searching on ➡ www.pdfvce.com ☐ ☐ ☐ 3V0-41.22 Reliable Test Prep
- Pass Guaranteed Quiz VMware - Trustable 3V0-41.22 Test Collection Pdf ☐ Simply search for [3V0-41.22] for free download on ☀ www.real4dumps.com ☐ ☀ ☐  3V0-41.22 Exam Study Guide
- Exam 3V0-41.22 Torrent ☐ Reliable 3V0-41.22 Dumps Pdf ☐ 3V0-41.22 Dump ♣ Open website ☐ www.pdfvce.com ☐ and search for 【 3V0-41.22 】 for free download ☐ Exam 3V0-41.22 Torrent
- 3V0-41.22 Valid Test Vce Free ☐ 3V0-41.22 Relevant Questions ☐ Valid 3V0-41.22 Test Simulator ☐ Search for [3V0-41.22] and download it for free on ➡ www.examsreviews.com ☐ ☐ ☐ website ☐ Test 3V0-41.22 Price
- Pass Guaranteed Quiz VMware - Trustable 3V0-41.22 Test Collection Pdf ☐ Open ✓ www.pdfvce.com ☐ ✓ ☐ enter ► 3V0-41.22 ◀ and obtain a free download ☐ 3V0-41.22 Relevant Questions
- Fast Download 3V0-41.22 Test Collection Pdf| Easy To Study and Pass Exam at first attempt - Excellent VMware

Advanced Deploy VMware NSX-T Data Center 3.X ☐ Open (www.testsdumps.com) and search for ⇒ 3V0-41.22 ⇐ to download exam materials for free ☐ Latest Test 3V0-41.22 Experience

- Hot 3V0-41.22 Test Collection Pdf Pass Certify | Efficient Dumps 3V0-41.22 Download: Advanced Deploy VMware NSX-T Data Center 3.X ☐ Search for { 3V0-41.22 } on “www.pdfvce.com” immediately to obtain a free download ☐ ☐ 3V0-41.22 Relevant Questions
- 3V0-41.22 Latest Test Camp ☐ Exam 3V0-41.22 Torrent ☐ Reliable 3V0-41.22 Exam Voucher ☐ Immediately open ➡ www.testsimulate.com ☐ and search for ► 3V0-41.22 ◀ to obtain a free download ☐ Reliable 3V0-41.22 Exam Voucher
- ummalife.com, simaabacus.com, www.stes.tyc.edu.tw, lms.ait.edu.za, www.stes.tyc.edu.tw, www.999wow.cn, www.stes.tyc.edu.tw, motionentrance.edu.np, www.stes.tyc.edu.tw, www.stes.tyc.edu.tw, Disposable vapes

What's more, part of that Torrent Valid 3V0-41.22 dumps now are free: <https://drive.google.com/open?id=1-SDlaf0pqCkfuawrth9K0acMI9XPaIM1>